

submitSublets

Superseded Specifications	
Document status	DRAFT
Document owner	Garrett, Michael
Document version	v0.1
Designer	Garrett, Michael
Solution Review	Lewis, Robert, Plunkett, Shane
Classification	Public

Version History

Version	Date	Status	Description	Updated By
0.1	30 Nov 2020	DRAFT	Initial proposal	Changes performed by Garrett, Michael

Content

- [Content](#)
- [Summary](#)
- [submitSublets](#)
 - [Applicable Quoting Methods](#)
 - [Supported Sublet Types](#)
 - [Request Parameters](#)
 - [Request Parameters - Sublets section](#)
 - [Example Request](#)
 - [Example Response](#)

Summary

The submit sublets request allows the BMS to update and add sublets to the quote. Sublets will appear in the Sublets component of an AudaNet Quote, or to the Sublets section of an AudaBridge Quote. Two categories of sublets can be added/modified:

Internal Sublets:

Internal Sublets are work that the repairer is managing the payment of internally. The price of these will appear on the estimate that is sent to the insurer for authorisation and payment.

External Sublets:

External Sublets are work where the sublet provider will invoice the Insurance Company directly. The cost of these will *not* appear on the estimate that is sent to the insurer for authorisation; however, they will display as a line item for information purposes.

Both internal and external sublets should be added to the sublets field. To distinguish between an internal and external sublet, set the subletManagementFlag to INT or EXT respectively. The parameters for the submitSublets function are listed in the table below.

NOTE: The submitSublets function is not currently supported by the Suncorp workflow for AudaNet quotes. Sublets need to be added manually by the repairer when completing an assessment as per agreed process with Suncorp.

Applicable Quoting Methods

Quoting Method	AudaNet Quoting Method	AudaBridge Quoting Method
	✓(Except Suncorp)	✓

submitSublets

Supported Sublet Types

Description	CODE
Alarm	ALRM
Bull Bar	BLBR
Bumper Bar	BUMP
Car Phone	PHNE
Chassis	CHASSIS
Computer / SCAN	CPTR
Condenser	CONDENSER
Cooling (Multiple)	COOLING
Data Dot	DATADOT
Decals	DCLS
Differential	DIFF
DVD	DVD
Electrics	ELTR
Engine	ENGN
Exhaust	EXHS
Fuel Contamination	FUELCONTAMINATION
Fuel Tank	FLTK
Head Lamps / Driving Lights	HLMP
Interior Trim	TRIM
Keys / Locks	KEYSLOCKS
Liquid Petroleum Gas	LPG
Mech (Multiple)	MECH
Mechanical Report	MECHANICALREPORT
Motor Glass	MOTORGLASS
Occupant Safety (SRS)	OCCUPANTSAFETY
Other	OTH
Paint Protection	PNTP
Panel Work	PANELWORK
PDR	PDR
Radiator	RADI
Receiver Dryer	RCDR
Rust Proofing	RSTP
SAT NAV	SATNAV
Sharps	SHARPS
Sign Writing	SGNW
Soft Top	SFTP
Sound System	SSYS
Sun Roof	SUNROOF
Suspension	SUSP

Theft Report	THEFTREPORT
Tow Bar	TOWB
Transmission	TRNS
Tyre	TYRE
Wheel Alignment	WLGN
Wheels	WHEL

Request Parameters

Field Name	Field Type	Comments
*userId	String	User ID used to log into the AudaNet platform
*password	String	User ID's password to log into the platform
*claimNumber	String	
*displayName		
*generator	String	AXN
version	String	
sublets	List	Contains any number of sublets. Existing sublets cannot be removed. The contents of the sublet section of the request are described below.
unlockQuote	Boolean	Deprecated

*Denotes mandatory field

Request Parameters - Sublets section

Field Name	Field Type	Comments
quoteLineNumber	Short	There are two scenarios for quoteLineNumber for sublets <ol style="list-style-type: none"> 1. Adding a new sublet: <ol style="list-style-type: none"> a. When adding a new sublet, submit the sublet with a blank quote line number. The response will provide a new quote line number for the sublet which MUST be used for all updates of that sublet moving forward, else duplications will occur 2. Updating an existing sublet <ol style="list-style-type: none"> a. When updating a sublet the previously allocated quoteLineNumber Must be used else this will lead to duplication and the sublet will not be updated.
subletType	String	Must be a value from the sublet types table above
subletDescription	String	Maximum 20 characters
subletAmount	Double	Must be a positive number. Should be empty for external sublets i.e. when subletManagementFlag is EXT
subletManagementFlag	String	Must be either INT or EXT. Represents either an internal or external sublet respectively
subletRepairer	String	Maximum 29 characters
subletRepairerAddress	String	A recommended maximum of 30 characters
subletRepairerPhone	String	Maximum 10 characters

subletAuthorityNumber	Integer	Deprecated
subletAuthorityDocument	base64 Binary	Deprecated

Example Request

submitParts Example Request

```
<soapenv:Envelope xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/" xmlns:ws="http://ws.axnbusiness.b2b.audatex.com">
  <soapenv:Header/>
  <soapenv:Body>
    <ws:submitSubletsRequest>
      <ws:credential>
        <ws:userId>USERNAME</ws:userId>
        <ws:password>PASSWORD</ws:password>
      </ws:credential>
      <ws:claimNumber>1860105928</ws:claimNumber>
      <ws:displayName>ALZ013962</ws:displayName><ws:versions>
        <ws:generator>?</ws:generator>
        <!--Optional:-->
        <ws:version>?</ws:version>
      </ws:versions>
      <!--Optional:-->
      <ws:sublets>
        <ws:sublet>
          <ws:quoteLineNumber>11</ws:quoteLineNumber>
          <ws:subletType>AMPL</ws:subletType>
          <ws:subletDescription>AMPLIFIER</ws:subletDescription>
          <ws:subletAmount>100</ws:subletAmount>
          <ws:subletManagementFlag>INT</ws:subletManagementFlag>
          <ws:subletRepairer>Test Repairer</ws:subletRepairer>
          <ws:subletRepairerAddress/>
          <ws:subletRepairerPhone/>
        </ws:sublet>
        <ws:sublet>
          <ws:quoteLineNumber></ws:quoteLineNumber>
          <ws:subletType>BLBR</ws:subletType>
          <ws:subletDescription>BULL BAR</ws:subletDescription>
          <ws:subletAmount/>
          <ws:subletManagementFlag>EXT</ws:subletManagementFlag>
          <ws:subletRepairer>TestA Repairer</ws:subletRepairer>
          <ws:subletRepairerAddress>123 Test Road</ws:subletRepairerAddress>
          <ws:subletRepairerPhone/>
        </ws:sublet>
      </ws:sublets>
      <ws:unlockQuote>>false</ws:unlockQuote>
    </ws:submitSubletsRequest>
  </soapenv:Body>
</soapenv:Envelope>
```

Example Response

submitSublets Response

```
<soapenv:Envelope xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/" xmlns:xsd="http://www.w3.org/2001/XMLSchema" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <soapenv:Body>
    <ws:submitSubletsResponse xmlns:ws="http://ws.axnbusiness.b2b.audatex.com">
      <ws:serviceResponse>
        <ws:Code>Service.OK</ws:Code>
        <ws:Severity>0</ws:Severity>
        <ws:Message>Operation completed successfully</ws:Message>
      </ws:serviceResponse>
      <ws:sublets>
        <ws:sublet>
          <ws:quoteLineNumber>11</ws:quoteLineNumber>
          <ws:subletType>AMPL</ws:subletType>
          <ws:subletDescription>AMPLIFIER</ws:subletDescription>
          <ws:subletAmount>100</ws:subletAmount>
          <ws:subletManagementFlag>INT</ws:subletManagementFlag>
          <ws:subletRepairer>Test Repairer</ws:subletRepairer>
          <ws:subletRepairerAddress/>
          <ws:subletRepairerPhone/>
        </ws:sublet>
        <ws:sublet>
          <ws:quoteLineNumber>12</ws:quoteLineNumber>
          <ws:subletType>BLBR</ws:subletType>
          <ws:subletDescription>BULL BAR</ws:subletDescription>
          <ws:subletAmount/>
          <ws:subletManagementFlag>EXT</ws:subletManagementFlag>
          <ws:subletRepairer>TestA Repairer</ws:subletRepairer>
          <ws:subletRepairerAddress>123 Test Road</ws:subletRepairerAddress>
          <ws:subletRepairerPhone/>
        </ws:sublet>
      </ws:sublets>
    </ws:submitSubletsResponse>
  </soapenv:Body>
</soapenv:Envelope>
```